

Getting Started with OverDrive eBooks on Adobe Digital Editions

Older model Kobo eReaders do not support direct download of OverDrive ebooks. They must be downloaded to Adobe Digital Editions software on a computer before they can be transferred to the Kobo eReader.

Not sure if your device supports direct downloads? Connect the device to a Wi-Fi network and tap the Sync button. When the eReader has finished updating, open the menu and then Settings. If OverDrive is listed, the device supports direct downloads.

Install Adobe Digital Editions (ADE)

Go to <https://www.adobe.com/ca/solutions/ebook/digital-editions/download.html> to download and install Adobe Digital Editions (ADE) software on your desktop computer.

Create an OverDrive account

1. Go to <https://www.overdrive.com/account/sign-in> and select **Sign up, it's free!**
2. Enter your email address and password of your choice to create the account. Select **Sign Up**. OverDrive will send a verification email to the email account used. Open the email and follow the instructions to verify the account.

Authorize Adobe Digital Editions (ADE) with an OverDrive account

1. Open ADE and select on **Help**. Click on **Authorize Computer**.
2. Select the **eBook Vendor** box and scroll down and select **OverDrive** (the list is not alphabetical). Customers with an Adobe account can authorize their computer with their Adobe ID by selecting Adobe ID as the eBook Vendor.
3. Enter the email address and the password used to create your OverDrive Account. Select **Authorize**.
4. With Adobe Digital Editions open, connect your Kobo eReader to your computer using the USB cable supplied. Select **Connect** on the Kobo eReader's screen. Leave the eReader plugged into the computer.
5. In ADE, **Kobo eReader** will appear under Devices on the left-hand side of the screen. This may take a few minutes.
6. Click on **Kobo eReader** to select it. Select the **Device Options** button (settings wheel) and select **Authorize Device**.

Find and download ebooks

1. Go to the Toronto Public Library's OverDrive website at tpl.ca/overdrive.
2. Select **Search** to find a book by title, author or series. Select **Collections** to browse. Look for the eBook indicator to select the eBook, instead of audiobook, format of a title.
3. Select the cover to find out more about the book. Select **Borrow** to check out the book. If a Place a Hold button displays instead of Borrow, select it to be added to the waiting list.
4. Enter your library card number and PIN (usually the last four digits of your phone number) to sign in. For holds, enter your email address to receive the holds notification.

5. Go to your Loans page under My Account and select the **Download** button next to the book cover. Your browser will download an acsm file for the ebook.
6. The browser may automatically open this file. If not, click on Open (if available) or double-click on the downloaded acsm file (check Downloads folder on computer) to start the authorization process and open the ebook in ADE.

Transferring ebooks to a Kobo eReader

1. The downloaded title will open in Reading view in ADE. Click on **Library** in the upper left-hand corner to switch to Library view.
2. Click on the book cover and drag and drop the title to your Kobo eReader (listed under Devices) or right-click on the cover and select **Copy to Computer/Device** and then **Kobo eReader**.
3. Safely eject your eReader from your computer.
4. After a moment, the ebook will be available in the My Books section of your eReader.

Returning ebooks

OverDrive eBooks will automatically expire at the end of the lending period. They can also be returned early. Help to keep waiting times short by returning borrowed items once you are finished.

Open ADE on your computer and connect the Kobo eReader to the computer with a USB cable.

1. Select **Connect** on the screen of the Kobo eReader. Leave the eReader connected to the computer.
2. In ADE, click on **All Items** under Bookshelves on the left.
3. Right click on the cover of the ebook to be returned. Left click on **Return Borrowed Item**.
4. Under Devices, click on **Kobo eReader**.
5. Right click on the cover the ebook that you just returned. Left click on **Remove from Library**.

More Help:

For more information, go to Adobe support at <https://helpx.adobe.com/ca/support/digital-editions.html> or OverDrive Help at <https://help.overdrive.com/en-us/9988.html>.